



May all your fermentations be Great Fermentations!

Ivan the Terribly Delicious – Imperial Red Ale!

A formidable imperial red ale that will dominate your taste buds! A beautiful red color and a blend of Columbus, Amarillo and Citra hops make this big beer a force to be reckoned with. Brew this beer and soon your friends will be pledging allegiance to you as the beer Tsar!

BEER SPECS

Original Gravity: 1.077–1.080

Final Gravity: 1.018–1.021

IBU: 89-94

ABV%: 7.3% - 8.2%

Yield: 5 Gallons

NOT INCLUDED IN KIT

Irish Moss (*for clarity, optional*)

Yeast

Bottle Caps (*53 caps needed*)

Priming Sugar (*5oz or 3/4 cup*)

USEFUL INFORMATION

First Wort Hops = hops added before bringing wort to a boil

Wort = unfermented beer

Rack = to transfer from one vessel to another

Pitch = to add yeast to the fermenter

OG = Original Gravity: Specific Gravity Before Fermentation

FG = Final Gravity: Specific Gravity After Fermentation

ABV = Alcohol by Volume

ABW = Alcohol by Weight

IBU = International Bittering Units

Alcohol by Volume Equation:

$$\%ABW = (OG-FG) \times 105$$

$$\%ABV = ABW \times 1.25$$

RECIPE DETAILS

8.0 lbs. Light dried malt extract

1.0 lbs. Corn sugar

3.0 lbs. Cara-Amber malt, crushed

1.0 lb. Simpsons Medium Crystal malt, crushed

FERMENTABLES

SPECIALTY GRAINS

0.5 oz. Columbus hops, added after dissolving extracts and before boil

0.5 oz. Columbus hops, added at the beginning of the 60 minute boil

1.0 tsp. Irish moss (*optional*), added 20 min from the end of the boil

2.0 oz. Columbus hops, added 10 min from the end of the boil

0.5 oz. Amarillo hops, added at the end of the boil

0.5 oz. Citra hops, added at the end of the boil

1.0 oz. Amarillo, added as a dry hop

1.0 oz. Citra, added as a dry hop

BOIL SCHEDULE

YEAST SUGGESTIONS: Wyeast #1469 West Yorkshire Ale, White Labs WLP007 Dry English Ale, or Safale S-04 Dry Yeast. If using a liquid yeast, a yeast starter or two packs of yeast is highly recommended.

EQUIPMENT

REQUIRED EQUIPMENT

- 3 gal or larger Brew Pot
- 6.5 gal Primary Fermenter
- Siphon Hose/Racking Cane
- Large Spoon or Paddle
- Air Lock
- Hydrometer
- Thermometer
- Cleanser
- Sanitizer
- Bottles or Kegging System

RECOMMENDED EQUIPMENT

- 7.5 gal Brew Pot
- Wort Chiller
- 5 gal Secondary Fermenter
- Thief
- Oxygen Cylinder
- Aeration Stone
- Auto Siphon



Brewing Instructions: Ivan Imperial Red

PRIOR TO BREWING

1. **Clean and Sanitize** all equipment, tubing, etc.
2. If using White Labs liquid yeast, remove package(s) from fridge and let warm for 4-8 hours at room temperature. If using a Wyeast Activator pack, remove package(s) from fridge, 'smack' the pack to release the nutrients and allow the pack to swell for 4-8 hours at room temperature.

BREWING DAY

1. Fill kettle with water and heat to 150-155F.
 - Partial boil method: fill kettle with as much water as possible while leaving room for grains, malt extract, and boil volume.
 - Full boil method: fill kettle to approximately 6.5 gal water for a volume of 5 gal post-boil.
2. Rehydrate Irish moss in 1/2 cup warm water. Set aside (*optional, for clarity*).
3. Turn off burner (remove kettle from heating element if using an electric stove). Place crushed specialty grains in a muslin bag and soak in **150-155F water for 30 minutes**. Remove bag, and allow remaining water in grains to drain into kettle. Do not squeeze the grains.
4. While stirring, add malt extracts and corn sugar until fully dissolved, then add the first wort hops (0.5 oz Columbus hops).
5. Turn the heat on and bring wort to a boil. **WATCH OUT!** Just before the boil, the wort rapidly rises.
6. Follow **Boil Schedule** on opposite page under 'Recipe Details'
7. At end of boil, chill wort as quickly as possible to **60-70F** with a wort chiller or an ice bath. Place lid on kettle while chilling.
8. Siphon or pour cooled wort into fermenter leaving as much sediment behind as possible:
 - Partial Boil: Add sterile water (packaged drinking water) to fermenter to reach 5.25 gal
 - Full Boil: Siphon entire volume of wort into fermenter.
9. **Aerate wort** well by stirring, shaking or oxygenating.
10. Sanitize yeast package and use sanitized scissors to open package. Pitch yeast and attach airlock. If using a yeast starter, pitch entire contents of yeast starter into wort.
11. Move fermenter to a dark place with a steady temperature of **64-72F**.

FERMENTATION

1. Primary Fermentation: Allow beer to ferment for 5-7 days, then proceed to STEP 2 or 3.
2. Secondary Fermentation (*optional*): Transfer beer to a 5 gal carboy, leaving behind the sediment, then proceed to STEP 3.
3. Add **1.0 oz Amarillo and 1.0 oz Citra hops** to fermenter in small muslin hop bag and allow 4-7 days contact time.
4. Check gravity prior to proceeding with bottling to ensure fermentation is complete. (Reference *Final Gravity* under 'Recipe Details')

BOTTLING

1. Ensure there is no bubbling in the airlock, and that your beer has reached final gravity.
2. **Clean and sanitize** all bottles, caps, bottling equipment and bottling bucket.
3. Dissolve **3/4 cup (5 oz) priming sugar** in 2 cups boiling water. Boil for 5 min then chill to 70-80F and add to bottling bucket.
4. Siphon beer from fermenter into bottling bucket, being careful not to rouse up sediment on bottom of fermenter.
5. Stir thoroughly but gently to avoid introducing oxygen.
6. Using the bottle filler, fill bottles and cap them.
7. Store bottles at room temperature for **2 weeks** or

TIPS FOR SUCCESS

1. Clean AND Sanitize!
2. Avoid using softened water or Reverse Osmosis water.
3. Make sure the specialty grains are loose inside the muslin bag to ensure water reaches the entire amount.
4. Tie muslin bag to handle of kettle to prevent potential scorching on bottom of kettle.
5. Be sure not to exceed 155F while steeping grains to avoid unwanted flavors.
6. Turn off heat source and stir well while adding malt extract to avoid scorching on the bottom of the kettle.
7. Keep a spray bottle of water at hand to spray top of wort if it nears a boil over.
8. While racking, be sure not to introduce oxygen into your beer by splashing or shaking.
9. Maintain a constant temperature during fermentation.
10. Elevate carboy a few days before racking to allow sediment to settle.
11. Visit www.greatfermentations.com for more brewing tips and tricks.

