

Original Gravity: 1.055–1.065 Final Gravity: 1.018–1.024

Irish Moss (for clarity, optional)

Bottle Caps (53 caps needed)

Priming Sugar (5oz or 3/4 cup)

**BEER SPECS** 

IBU: 27-37

Yeast

other

**ABV%:** 4.9% - 6.2% **Yield:** 5 Gallons

NOT INCLUDED IN KIT

**USEFUL INFORMATION** 

Wort = unfermented beer

Before Fermentation

ABV = Alcohol by Volume

ABW = Alcohol by Weight

%ABW = (OG-FG) x 105

%ABV = ABW x 1.25

IBU = International Bittering Units

Alcohol by Volume Equation:

Fermentation

Rack = to transfer from one vessel to an-

Pitch = to add yeast to the fermenter

OG = Original Gravity: Specific Gravity

FG = Final Gravity: Specific Gravity After

# Thanks For The Mammaries – A Milk Stout

Think stout with a hint of sweetness from the addition of lactose in the boil. The resulting sweetness takes the sharp dark grain edge off the stout . The sweetness isn't so pronounced to take away from the beer.

# **RECIPE DETAILS**

6.6 lbs.	Light Liquid malt extract	FERMENTABLES
1.00 lb.	Light Munich malt, crushed	
1.00 lb.	Chocolate malt, crushed	
0.50 lb.	Roasted Barley malt, crushed	
0.50 lb.	Crystal 40L malt, crushed	
0.50 lb.	Flaked Oats	<b>SPECIALTY GRAINS</b>
1.25 oz.	East Kent Golding hops, added at beginning of 60 min boil	
1.0 tsp.	Irish moss (o <i>ptional</i> ), added 20 m	in from the end of the boil
0.5 oz.	East Kent Golding hops, added 10 min from the end of the boil	
1.0 lb.	Lactose sugar, added 10 min from the end of the boil BOIL SCHEDULE	

YEAST SUGGESTIONS: Wyeast #1084 Irish Ale, Nottingham Dry Yeast. If using a liquid yeast, a yeast starter or two packs of yeast is highly recommended.

# EQUIPMENT

#### **REQUIRED EQUIPMENT**

- 3 gal or larger Brew Pot
- 6.5 gal Primary Fermenter
- Siphon Hose/Racking Cane
- Large Spoon or Paddle
- Air Lock
- Hydrometer
- Thermometer
- Cleanser
- Sanitizer
- Bottles or Kegging System

#### RECOMMENDED EQUIPMENT

- 7.5 gal Brew Pot
- Wort Chiller
- 5 gal Secondary Fermenter
- Thief
- Oxygen Cylinder
- Aeration Stone
- Auto Siphon





# **Brewing Instructions: Thanks For The Mammaries**

#### **PRIOR TO BREWING**

- 1. Clean and Sanitize all equipment, tubing, etc.
- 2. If using liquid yeast, remove package from fridge and 'smack' the pack to release the nutrients. Allow pack to swell for 4-8 hours at room temperature.

(If using liquid yeast, a yeast starter or two packs of yeast is highly recommended.)

## **BREWING DAY**

- 1. Fill kettle with water and heat to 160F.
  - Partial boil method: fill kettle with as much water as possible while leaving room for grains, malt extract, and boil volume.
    - Full boil method: fill kettle to approximately 6.5 gal water for a volume of 5 gal post-boil.
- 2. Rehydrate Irish moss In 1/2 cup warm water. Set aside (*optional, for clarity*).
- Turn off burner (remove kettle from heating element if using an electric stove). Place crushed specialty grains in a muslin bag and soak in 150-155F water for 30 minutes. Remove bag, and allow remaining water in grains to drain into kettle. Do not squeeze the grains.
- 4. While stirring, add malt extracts until fully dissolved.
- 5. Turn the heat on and bring wort to a boil. WATCH OUT! Just before the boil, the wort rapidly rises.
- 6. Follow **Boil Schedule** on opposite page under 'Recipe Details'
- At end of boil, chill wort as quickly as possible to 60-70F with a wort chiller or an ice bath. Place lid on kettle while chilling.
- 8. Siphon or pour cooled wort into fermenter leaving as much sediment behind as possible:
  - Partial Boil: Add sterile water (packaged drinking water) to fermenter to reach 5.25 gal
  - Full Boil: Siphon entire volume of wort into fermenter.
- 9. Aerate wort well by stirring, shaking or oxygenating.
- 10. Sanitize yeast package and use sanitized scissors to open package. Pitch yeast and attach airlock. If using a yeast starter, pitch entire contents of yeast starter into wort.
- 11. Move fermenter to a dark place with a steady temperature of **64-72F**.

## FERMENTATION

- 1. Primary Fermentation: Allow beer to ferment for 5-7 days, then proceed to STEP 2 or 3.
- Secondary Fermentation (*optional*): Transfer beer to a 5 gal carboy, leaving behind the sediment, then proceed to STEP 3.
- 3. Check gravity prior to proceeding with bottling to ensure termentation is complete. (Reference *Final Gravity* under '*Recipe Details'*)

# BOTTLING

- 1. Ensure there is no bubbling in the airlock, and that your beer has reached final gravity.
- 2. **Clean and sanitize** all bottles, caps, bottling equipment and bottling bucket.
- Dissolve 3/4 cup (5 oz) priming sugar in 2 cups boiling water. Boil for 5 min then chill to 70-80F and add to bottling bucket.
- 4. Siphon beer from fermenter into bottling bucket, being careful not to rouse up sediment on bottom of fermenter.
- 5. Stir thoroughly but gently to avoid introducing oxygen.
- 6. Using the bottle filler, fill bottles and cap them.
- 7. Store bottles at room temperature for **2 weeks** or until carbonated

# TIPS FOR SUCCESS

- 1. Clean AND Sanitize!
- 2. Avoid using softened water or Reverse Osmosis water.
- 3. Make sure the specialty grains are loose inside the muslin bag to ensure water reaches the entire amount.
- 4. Tie muslin bag to handle of kettle to prevent potential scorching on bottom of kettle.
- 5. Be sure not to exceed 155F while steeping grains to avoid unwanted flavors.
- 6. Turn off heat source and stir well while adding malt extract to avoid scorching on the bottom of the kettle.
- 7. Keep a spray bottle of water at hand to spray top of wort if it nears a boil over.
- 8. While racking, be sure not to introduce oxygen into your beer by splashing or shaking.
- 9. Maintain a constant temperature during fermentation.
- 10. Visit www.greatfermentations.com for more brewing tips and tricks.



